


Lab - Implement SPAN Technologies (Instructor Version)

Instructor Note: Red font color or gray highlights indicate text that appears in the instructor copy only.

Answers: [24.1.5 Lab - Implement SPAN Technologies](#)

Topology



Addressing Table

| Device | Interface | IP Address | IPv6 Address | IPv6 Link Local |
|--------|--------------|------------------|---------------------------|-----------------|
| D1 | VLAN 1 | 192.168.1.1/24 | 2001:db8:acad:1000::1/64 | fe80::d1:1 |
| | VLAN 2 | 192.168.2.1/24 | 2001:db8:acad:2000::1/64 | fe80::d1:2 |
| | VLAN 3 | 192.168.3.1/24 | 2001:db8:acad:3000::1/64 | fe80::d1:3 |
| A1 | VLAN 1 | 192.168.1.3/24 | 2001:db8:acad:1000::3/64 | fe80::a:1 |
| PC1 | NIC | 192.168.1.50/24 | 2001:db8:acad:1000::50/64 | EUI-64 |
| PC2 | NIC (VLAN 2) | Assigned by DHCP | Assigned by SLAAC | EUI-64 |
| PC3 | NIC (VLAN 3) | Assigned by DHCP | Assigned by SLAAC | EUI-64 |
| PC4 | NIC (VLAN 3) | Assigned by DHCP | Assigned by SLAAC | EUI-64 |

Objectives

Part 1: Build the Network and Configure Basic Device Settings and Interface Addressing

Part 2: Configure and Verify Local SPAN

Part 3: Configure and Verify RSPAN

Background / Scenario

The Switch Port Analyzer (SPAN) feature allows you to instruct a switch to send copies of packets seen on one port, multiple ports, or an entire VLAN, to another port on the same switch. The Remote SPAN (RSPAN) feature takes the SPAN feature beyond a single switch to a network, allowing you to remotely capture traffic on different switches in the network. This is extremely useful in campus networks where a sniffer may not be located at the desired traffic capture point. In addition, this allows you to permanently place a sniffer in the campus network to SPAN traffic as necessary or when troubleshooting situations arise.

Note: This lab is an exercise in configuring options available for SPAN and does not necessarily reflect network troubleshooting best practices.

Instructor Note: This lab may not work as intended if you are using NETLAB with a control switch.

Note: The switches used in the CCNP hands-on labs are Cisco Catalyst 3650s with Cisco IOS XE Release 16.9.4 (universalk9 image) and Cisco Catalyst 2960s with Cisco IOS Release 15.2(2) (lanbasek9 image). Other switches and Cisco IOS versions can be used. Depending on the model and Cisco IOS version, the commands available and the output produced might vary from what is shown in the labs.

Note: Make sure that the switches have been erased and have no startup configurations. If you are unsure, contact your instructor.

Note: The default Switch Database Manager (SDM) template on a Catalyst 2960 does not support IPv6. You must change the default SDM template to the dual-ipv4-and-ipv6 default template using the **sdm prefer dual-ipv4-and-ipv6 default** global configuration command. Changing the template will require a reboot.

Instructor Note: Refer to the Instructor Lab Manual for the procedures to initialize and reload devices.

Required Resources

- 1 Switch (Cisco 3650 with Cisco IOS XE Release 16.9.4 universal image or comparable)
- 1 Switch (Cisco 2960 with Cisco IOS Release 15.2(2) lanbasek9 image or comparable)
- 4 PCs (Choice of operating system with terminal emulation program and with a packet capture utility)
- Console cables to configure the Cisco IOS devices via the console ports
- Ethernet cables as shown in the topology

Part 1: Build the Network and Configure Basic Device Settings and Interface Addressing

In Part 1, you will set up the network topology and configure basic settings and interface addressing on switches.

Step 1: Cable the network as shown in the topology.

Attach the devices as shown in the topology diagram, and cable as necessary.

Step 2: Configure basic settings for each device.

- a. Console into each device, enter global configuration mode, and apply the basic settings. The startup configurations for each device are provided below.

Switch D1

```
config t
```

Lab - Implement SPAN Technologies

```
hostname D1
no ip domain lookup
ip routing
ipv6 unicast-routing
banner motd # D1, Implement SPAN Technologies #
line con 0
  exec-timeout 0 0
  logging synchronous
  exit
line vty 0 4
  privilege level 15
  exec-timeout 0 0
  password cisco123
  login
  exit
vlan 2
  name SECOND_VLAN
  exit
vlan 3
  name THIRD_VLAN
  exit
interface vlan 1
  ip address 192.168.1.1 255.255.255.0
  ipv6 address fe80::d1:1 link-local
  ipv6 address 2001:db8:acad:1000::1/64
  no shutdown
  exit
interface vlan 2
  ip address 192.168.2.1 255.255.255.0
  ipv6 address fe80::d1:2 link-local
  ipv6 address 2001:db8:acad:2000::1/64
  no shutdown
  exit
interface vlan 3
  ip address 192.168.3.1 255.255.255.0
  ipv6 address fe80::d1:3 link-local
  ipv6 address 2001:db8:acad:3000::1/64
  no shutdown
  exit
interface range g1/0/23
  spanning-tree portfast
  switchport mode access
  no shutdown
  exit
interface range g1/0/24
```

Lab - Implement SPAN Technologies

```
spanning-tree portfast
switchport mode access
switchport access vlan 2
no shutdown
exit
interface range g1/0/5-6
switchport mode trunk
channel-group 1 mode active
no shutdown
exit
interface range g1/0/1-4, g1/0/7-22, g1/1/1-4
shutdown
exit
ip dhcp pool SECOND_VLAN_POOL
network 192.168.2.0 255.255.255.0
default-router 192.168.2.1
exit
ip dhcp pool THIRD_VLAN_POOL
network 192.168.3.0 255.255.255.0
default-router 192.168.3.1
exit
end
```

Switch A1

```
config t
hostname A1
no ip domain lookup
ipv6 unicast-routing
banner motd # A1, Implement SPAN Technologies #
line con 0
exec-timeout 0 0
logging synchronous
exit
line vty 0 4
privilege level 15
exec-timeout 0 0
password cisco123
login
exit
vlan 2
name SECOND_VLAN
exit
vlan 3
name THIRD_VLAN
exit
interface vlan 1
```

```
ip address 192.168.1.3 255.255.255.0
ipv6 address fe80::a1:1 link-local
ipv6 address 2001:db8:acad:1000::3/64
no shutdown
exit
interface range f0/1-2
switchport mode trunk
channel-group 1 mode active
no shutdown
exit
interface range f0/23 - 24
switchport mode access
switchport access vlan 3
spanning-tree portfast
no shutdown
exit
interface range f0/3-22, g0/1-2
shutdown
exit
end
```

- b. Set the clock on each device to UTC time.
- c. Save the running configuration to startup-config.
- d. Configure IPv4 and IPv6 addresses on all hosts as shown in the addressing table.
- e. Verify that the PCs can ping their default gateways and each other.

Part 2: Configure and Verify Local SPAN

In this part you will configure and verify a local SPAN on D1, configuring it so that PC1 is able to capture traffic from PC2, even though it is in a different VLAN.

Step 1: Configure Local SPAN.

- a. Create a Local SPAN session with a source of g1/0/24 and a destination of g1/0/23. The monitor session number is locally significant only, so you can use any number IOS XE allows you to. Note that there is a limit to the number of sessions that can run simultaneously, and that the SPAN can consume significant resources.

```
D1(config)# monitor session 1 source interface g1/0/24
D1(config)# monitor session 1 destination interface g1/0/23
```

- b. Verify the configuration by issuing the **show monitor session #** or **show monitor session local** command.

```
D1# show monitor session local
Session 1
-----
Type                : Local Session
Source Ports        :
    Both             : Gi1/0/24
Destination Ports   : Gi1/0/23
```

```
Encapsulation      : Native
Ingress            : Disabled
```

Step 2: Verify that the SPAN is operational.

- On PC 1, open Wireshark and start capturing on the Ethernet interface. Add the capture filter **icmp**.
- On PC 2, ping 192.168.1.1. Send 3 packets of 300 bytes.
On a Windows PC, the command is **ping -n 3 -l 300 192.168.1.1**
On a Linux PC, the command is **ping -s 300 -c 3 192.168.1.1**
- On PC 1, stop the Wireshark capture and examine the output.
- Remove the monitor session using the **no monitor session 1** command.

Part 3: Configure and Verify RSPAN

In this part, you will configure and verify a Remote SPAN (RSPAN). RSPAN allows the source and destination ports to be on different switches. For this to work, it uses a VLAN configured only for remote-span functionality. The source port then places the transmitted or received data onto the remote-span VLAN. The remote-span VLAN is carried across trunks. The receiving switch takes the data sourced from the remote-span VLAN and sends it to the destination port that is running the protocol analyzer.

VLAN 500 will be created on D1 and A1 to be used as the remote-span VLAN. PC 1 will again take on the capture role, this time it will be interested in traffic coming from VLAN 2 on Switch A1.

Step 1: Configure RSPAN VLAN.

- Create the RSPAN VLAN on D1 and A1 using the **vlan 500** command from global configuration mode.

```
D1# config t
Enter configuration commands, one per line.  End with CNTL/Z.
D1(config)# vlan 500
D1(config-vlan)# name Remote_SPAN
D1(config-vlan)# remote-span
D1(config-vlan)# exit
```

- Use the **show vlan remote-span** command to verify VLAN 500 is configured correctly and is designated as the remote-span vlan. Use the **show interface trunk** command to ensure the RSPAN VLAN is allowed on the trunks. The RSPAN VLAN should not be a DATA VLAN. Its purpose is strictly for carrying the monitored traffic across trunk links from one switch to another.

```
D1# show vlan remote-span
```

```
Remote SPAN VLANs
```

```
-----
500
```

```
D1# show interface trunk
```

| Port | Mode | Encapsulation | Status | Native vlan |
|------|------|---------------|----------|-------------|
| Po1 | on | 802.1q | trunking | 1 |

| Port | Vlans allowed on trunk |
|------|------------------------|
| Po1 | 1-4094 |

Lab - Implement SPAN Technologies

```
Port          Vlans allowed and active in management domain
Po1          1-3,500
```

```
Port          Vlans in spanning tree forwarding state and not pruned
Po1          1-3,500
```

- c. Now configure the monitor session on A1 with a source interface of vlan 2 and a destination of remote vlan 500. Because the captured traffic must traverse the local switch to a remote switch, we must use the remote VLAN as the destination.

```
A1(config)# monitor session 2 source vlan 3
A1(config)# monitor session 2 destination remote vlan 500
%Note: ingoring the reflector port configuration
```

Note: The ignoring the reflector port message is an artifact of an older OS and can be safely ignored.

- d. Verify the configuration using the **show monitor session 2** command.

```
A1# show monitor session 2
Session 2
-----
Type                : Remote Source Session
Source VLANs        :
  Both               : 3
Dest RSPAN VLAN     : 500
```

- e. Move to the D1 switch and configure it to collect the desired traffic. The source port on D1 will be the remote-span vlan 500 and the destination port will be the client connected to G1/0/23.

```
D1(config)# monitor session 2 source remote vlan 500
D1(config)# monitor session 2 destination interface g1/0/23
```

Note that the session numbers do not have to match at either end of the session.

- f. Verify the configuration using the **show monitor session 2** command on D1.

```
D1# show monitor session 2
Session 2
-----
Type                : Remote Destination Session
Source RSPAN VLAN   : 500
Destination Ports    : Gi1/0/23
  Encapsulation     : Native
  Ingress            : Disabled
```

Step 2: Verify that the SPAN is operational.

- On PC 1, open Wireshark and start capturing on the Ethernet interface.
- On PC3 and PC4 (the hosts on A1), ping 192.168.1.1. Send 3 packets of 300 bytes.
On a Windows PC, the command is **ping -n 3 -l 300 192.168.1.1**
On a Linux PC, the command is **ping -s 300 -c 3 192.168.1.1**
- On PC 1, stop the Wireshark capture and examine the output. You should see pings sourced from PC3 and PC4, along with responses to those pings.
- Remove the monitor session using the **no monitor session 2** command on A1 and D1.

Device Configs – Final

Switch D1

```
D1# show run
Building configuration...

Current configuration : 9628 bytes
!
version 16.9
no service pad
service timestamps debug datetime msec
service timestamps log datetime msec
! Call-home is enabled by Smart-Licensing.
service call-home
no platform punt-keepalive disable-kernel-core
!
hostname D1
!
vrf definition Mgmt-vrf
!
  address-family ipv4
  exit-address-family
!
  address-family ipv6
  exit-address-family
!
no aaa new-model
switch 1 provision ws-c3650-24ts
!
ip routing
!
no ip domain lookup
!
ip dhcp pool SECOND_VLAN_POOL
  network 192.168.2.0 255.255.255.0
  default-router 192.168.2.1
!
ip dhcp pool THIRD_VLAN_POOL
  network 192.168.3.0 255.255.255.0
  default-router 192.168.3.1
!
login on-success log
ipv6 unicast-routing
!

license boot level ipservicesk9
!
diagnostic bootup level minimal
!
```


Lab - Implement SPAN Technologies

```
spanning-tree mode rapid-pvst
spanning-tree extend system-id
!
redundancy
mode sso
!
transceiver type all
monitoring
!
class-map match-any system-cpp-police-topology-control
description Topology control
class-map match-any system-cpp-police-sw-forward
description Sw forwarding, L2 LVX data, LOGGING
class-map match-any system-cpp-default
description Inter FED, EWLC control, EWLC data
class-map match-any system-cpp-police-sys-data
description Learning cache ovfl, High Rate App, Exception, EGR Exception, NFL
SAMPLED DATA, RPF Failed
class-map match-any system-cpp-police-punt-webauth
description Punt Webauth
class-map match-any system-cpp-police-l2lvx-control
description L2 LVX control packets
class-map match-any system-cpp-police-forus
description Forus Address resolution and Forus traffic
class-map match-any system-cpp-police-multicast-end-station
description MCAST END STATION
class-map match-any system-cpp-police-multicast
description Transit Traffic and MCAST Data
class-map match-any system-cpp-police-l2-control
description L2 control
class-map match-any system-cpp-police-dot1x-auth
description DOT1X Auth
class-map match-any system-cpp-police-data
description ICMP redirect, ICMP_GEN and BROADCAST
class-map match-any system-cpp-police-stackwise-virt-control
description Stackwise Virtual
class-map match-any non-client-nrt-class
class-map match-any system-cpp-police-routing-control
description Routing control and Low Latency
class-map match-any system-cpp-police-protocol-snooping
description Protocol snooping
class-map match-any system-cpp-police-dhcp-snooping
description DHCP snooping
class-map match-any system-cpp-police-system-critical
description System Critical and Gold Pkt
!
policy-map system-cpp-policy
!
interface Port-channell
switchport mode trunk
```

Lab - Implement SPAN Technologies

```
!  
interface GigabitEthernet0/0  
vrf forwarding Mgmt-vrf  
no ip address  
shutdown  
negotiation auto  
!  
interface GigabitEthernet1/0/1  
shutdown  
!  
interface GigabitEthernet1/0/2  
shutdown  
!  
interface GigabitEthernet1/0/3  
shutdown  
!  
interface GigabitEthernet1/0/4  
shutdown  
!  
interface GigabitEthernet1/0/5  
switchport mode trunk  
channel-group 1 mode active  
!  
interface GigabitEthernet1/0/6  
switchport mode trunk  
channel-group 1 mode active  
!  
interface GigabitEthernet1/0/7  
shutdown  
!  
interface GigabitEthernet1/0/8  
shutdown  
!  
interface GigabitEthernet1/0/9  
shutdown  
!  
interface GigabitEthernet1/0/10  
shutdown  
!  
interface GigabitEthernet1/0/11  
shutdown  
!  
interface GigabitEthernet1/0/12  
shutdown  
!  
interface GigabitEthernet1/0/13  
shutdown  
!  
interface GigabitEthernet1/0/14  
shutdown
```

Lab - Implement SPAN Technologies

```
!  
interface GigabitEthernet1/0/15  
shutdown  
!  
interface GigabitEthernet1/0/16  
shutdown  
!  
interface GigabitEthernet1/0/17  
shutdown  
!  
interface GigabitEthernet1/0/18  
shutdown  
!  
interface GigabitEthernet1/0/19  
shutdown  
!  
interface GigabitEthernet1/0/20  
shutdown  
!  
interface GigabitEthernet1/0/21  
shutdown  
!  
interface GigabitEthernet1/0/22  
shutdown  
!  
interface GigabitEthernet1/0/23  
switchport mode access  
spanning-tree portfast  
!  
interface GigabitEthernet1/0/24  
switchport access vlan 2  
switchport mode access  
spanning-tree portfast  
!  
interface GigabitEthernet1/1/1  
shutdown  
!  
interface GigabitEthernet1/1/2  
shutdown  
!  
interface GigabitEthernet1/1/3  
shutdown  
!  
interface GigabitEthernet1/1/4  
shutdown  
!  
interface Vlan1  
ip address 192.168.1.1 255.255.255.0  
ipv6 address FE80::D1:1 link-local  
ipv6 address 2001:DB8:ACAD:1000::1/64
```

Lab - Implement SPAN Technologies

```
!  
interface Vlan2  
 ip address 192.168.2.1 255.255.255.0  
 ipv6 address FE80::D1:2 link-local  
 ipv6 address 2001:DB8:ACAD:2000::1/64  
!  
interface Vlan3  
 ip address 192.168.3.1 255.255.255.0  
 ipv6 address FE80::D1:3 link-local  
 ipv6 address 2001:DB8:ACAD:3000::1/64  
!  
ip forward-protocol nd  
ip http server  
ip http authentication local  
ip http secure-server  
!  
!  
control-plane  
 service-policy input system-cpp-policy  
!  
banner motd ^C D1, Implement SPAN Technologies ^C  
!  
line con 0  
 exec-timeout 0 0  
 logging synchronous  
 stopbits 1  
line aux 0  
 stopbits 1  
line vty 0 4  
 exec-timeout 0 0  
 privilege level 15  
 password cisco123  
 login  
line vty 5 15  
 login  
!  
end
```

Switch A1

```
A1# show run  
Building configuration...  
  
Current configuration : 3698 bytes  
!  
version 15.2  
no service pad  
service timestamps debug datetime msec  
service timestamps log datetime msec  
no service password-encryption
```

Lab - Implement SPAN Technologies

```
!  
hostname A1  
!  
boot-start-marker  
boot-end-marker  
!  
no aaa new-model  
system mtu routing 1500  
!  
no ip domain-lookup  
ipv6 unicast-routing  
!  
spanning-tree mode pvst  
spanning-tree extend system-id  
!  
vlan internal allocation policy ascending  
!  
interface Port-channel1  
  switchport mode trunk  
!  
interface FastEthernet0/1  
  switchport mode trunk  
  channel-group 1 mode active  
!  
interface FastEthernet0/2  
  switchport mode trunk  
  channel-group 1 mode active  
!  
interface FastEthernet0/3  
  shutdown  
!  
interface FastEthernet0/4  
  shutdown  
!  
interface FastEthernet0/5  
  shutdown  
!  
interface FastEthernet0/6  
  shutdown  
!  
interface FastEthernet0/7  
  shutdown  
!  
interface FastEthernet0/8  
  shutdown  
!  
interface FastEthernet0/9  
  shutdown  
!  
interface FastEthernet0/10
```

Lab - Implement SPAN Technologies

```
shutdown
!  
interface FastEthernet0/11  
shutdown  
!  
interface FastEthernet0/12  
shutdown  
!  
interface FastEthernet0/13  
shutdown  
!  
interface FastEthernet0/14  
shutdown  
!  
interface FastEthernet0/15  
shutdown  
!  
interface FastEthernet0/16  
shutdown  
!  
interface FastEthernet0/17  
shutdown  
!  
interface FastEthernet0/18  
shutdown  
!  
interface FastEthernet0/19  
shutdown  
!  
interface FastEthernet0/20  
shutdown  
!  
interface FastEthernet0/21  
shutdown  
!  
interface FastEthernet0/22  
shutdown  
!  
interface FastEthernet0/23  
switchport access vlan 3  
switchport mode access  
spanning-tree portfast  
!  
interface FastEthernet0/24  
switchport access vlan 3  
switchport mode access  
spanning-tree portfast  
!  
interface GigabitEthernet0/1  
shutdown
```

Lab - Implement SPAN Technologies

```
!  
interface GigabitEthernet0/2  
 shutdown  
!  
interface Vlan1  
 ip address 192.168.1.3 255.255.255.0  
 ipv6 address FE80::A1:1 link-local  
 ipv6 address 2001:DB8:ACAD:1000::3/64  
!  
 ip http server  
 ip http secure-server  
!  
 banner motd ^C A1, Implement SPAN Technologies ^C  
!  
 line con 0  
  exec-timeout 0 0  
  logging synchronous  
 line vty 0 4  
  exec-timeout 0 0  
  privilege level 15  
  password cisco123  
  login  
 line vty 5 15  
  login  
!  
end
```