CISCO Academy

Lab - Implement a DMVPN Phase 3 Spoke-to-Spoke Topology (Instructor Version)

Instructor Note: Red font color or gray highlights indicate text that appears in the instructor copy only.

Answers: <u>19.1.4 Lab - Implement a DMVPN Phase 3 Spoke-to-Spoke</u> Topology

Topology



Addressing Table

Device	Interface	IPv4 Address		
R1	G0/0/1	192.0.2.1/30		
	Tunnel 1	100.100.100.1/29		
R2	G0/0/1	198.51.100.2/30		
	Loopback 0	192.168.2.1/24		
	Loopback 1	172.16.2.1/24		
	Tunnel 1	100.100.100.2/29		
R3	G0/0/1	203.0.113.2/30		
	Loopback 0	192.168.3.1/24		
	Loopback 1	172.16.3.1/24		
	Tunnel 1	100.100.3/29		

Objectives

In this lab, you will create a Dynamic Multipoint Virtual Private Network (DMVPN) that consists of a hub router with two spokes. You will implement a DMVPN Phase 3 spoke-to-spoke topology.

Part 1: Build the Network and Configure Basic Device Settings

Part 2: Configure DMVPN Phase 3

Part 3: Verify DMVPN Phase 3

Background / Scenario

In this lab, you will modify a DMVPN Phase 1 network to create Phase 3 spoke-to-spoke network. The configuration from the previous Phase 1 lab are required as the starting point for this lab.

Phase 3 improved upon Phase 2 by using a different mechanism for routing between destinations in spoke-tospoke tunnels. Because of this, Phase 3 can be seen as superseding Phase 2. For that reason, there is no Phase 2 lab.

In DMVPN Phase 3, the spoke routers create routing table entries in which NHRP manipulates the routing information for tunnel destinations by overriding the next hop that was determined by the routing protocol. NHRP provides the actual destination network as the next hop. This enables the distribution of route summaries from the hub router to the spokes. Finally, Phase 3 enables a hierarchical tree-based VPN architecture in which central hub routers connect other, regional hubs and their spokes. This allows for the establishment of tunnels between routers that are not connected to the same regional hub.

In Phase 1 DMVPN, all spoke router traffic must pass through the hub router, as shown in the topology diagram.



In a Phase 3 spoke-spoke DMVPN, traffic initially travels to the hub. The traffic then travels directly between the spoke routers over the spoke-to-spoke tunnel.



Note: This lab does not include the configuration of IPSec to secure the tunnels. This essential procedure will be covered in a later lab.

Note: This lab is an exercise in configuring and verifying various implementations of DMVPN topologies and does not reflect networking best practices.

Note: The routers used with CCNP hands-on labs are the Cisco 4221 with Cisco IOS XE Release 16.9.4 (universalk9 image). The Layer 3 switch is a Cisco Catalyst 3650 with Cisco IOS XE Release 16.9.4 (universalk9 image). Other routers, Layer 3 switches, and Cisco IOS versions can be used. Depending on the model and Cisco IOS version, the commands available and the output produced might vary from what is shown in the labs.

Note: Make sure that the devices have been erased and have no startup configurations. If you are unsure, please contact your instructor.

Instructor Note: Refer to the Instructor Lab Manual for the procedures to initialize and reload devices.

Required Resources

- 3 Routers (Cisco 4221 with Cisco IOS XE Release 16.9.4 universal image or comparable)
- 1 Layer 3 switch (Cisco 3650 with Cisco IOS Release 16.9.4 universal image or comparable)
- 1 PC (Choice of operating system with a terminal emulation program installed)
- Console cables to configure the Cisco IOS devices via the console ports
- Ethernet cables as shown in the topology

Initial Configurations

Students will use the devices that were configured for the "Lab - Implement a DMVPN Phase 1 Hub-to-Spoke Topology". If they do not have the preconfigured devices, they could benefit by practicing configuration of DMVPN Phase 1 from that lab. Otherwise, they could paste the initial configurations into the devices. Initial configurations are provided here.

R1 hub router

```
hostname R1
no ip domain lookup
banner motd # R1, Implement DMVPN Hub #
line con 0
exec-timeout 0 0
logging synchronous
```

```
exit
line vty 0 4
privilege level 15
password cisco123
exec-timeout 0 0
logging synchronous
login
exit
interface g0/0/1
ip address 192.0.2.1 255.255.255.252
no shutdown
exit
interface tunnel 1
 tunnel mode gre multipoint
tunnel source g0/0/1
tunnel key 999
 ip address 100.100.100.1 255.255.258.248
ip nhrp network-id 1
ip nhrp authentication NHRPauth
ip nhrp map multicast dynamic
bandwidth 4000
ip mtu 1400
ip tcp adjust-mss 1360
exit
router eigrp DMVPN TUNNEL NET
 address-family ipv4 unicast autonomous-system 68
eigrp router-id 1.1.1.1
network 100.100.100.0 255.255.258.248
af-interface tunnel 1
no split-horizon
router eigrp DMVPN TRANS NET
 address-family ipv4 unicast autonomous-system 168
eigrp router-id 10.1.1.1
 network 192.0.2.0 255.255.255.252
end
```

R2 spoke router 1

```
hostname R2
no ip domain lookup
banner motd # R2, Implement DMVPN Spoke 1 #
line con 0
exec-timeout 0 0
logging synchronous
exit
line vty 0 4
privilege level 15
```

```
password cisco123
 exec-timeout 0 0
 logging synchronous
login
exit
interface g0/0/1
ip address 198.51.100.2 255.255.255.252
no shutdown
exit
interface loopback 0
ip address 192.168.2.1 255.255.255.0
no shutdown
 exit
interface loopback 1
ip address 172.16.2.1 255.255.255.0
no shutdown
exit
interface tunnel 1
 tunnel mode gre ip
 tunnel source loopback 0
 tunnel destination 192.0.2.1
 tunnel key 999
 ip address 100.100.100.2 255.255.258
 ip nhrp network-id 1
 ip nhrp authentication NHRPauth
ip nhrp nhs 100.100.100.1
ip nhrp map multicast 192.0.2.1
 ip nhrp map 100.100.100.1 192.0.2.1
ip mtu 1400
ip tcp adjust-mss 1360
router eigrp DMVPN TUNNEL NET
 address-family ipv4 unicast autonomous-system 68
 eigrp router-id 2.2.2.2
 network 100.100.100.0 255.255.258.248
network 172.16.2.0 255.255.255.0
 eigrp stub connected
router eigrp DMVPN TRANS NET
 address-family ipv4 unicast autonomous-system 168
 eigrp router-id 20.2.2.2
network 198.51.100.0 255.255.255.252
 network 192.168.2.0 255.255.255.0
end
```

Router R3 spoke 2

hostname R3 no ip domain lookup

```
banner motd # R3, Implement DMVPN Spoke 2 #
line con 0
exec-timeout 0 0
logging synchronous
exit
line vty 0 4
privilege level 15
password cisco123
exec-timeout 0 0
logging synchronous
login
exit
interface g0/0/1
ip address 203.0.113.2 255.255.255.252
no shutdown
exit
interface loopback 0
ip address 192.168.3.1 255.255.255.0
no shutdown
exit
interface loopback 1
 ip address 172.16.3.1 255.255.255.0
no shutdown
exit
interface tunnel 1
tunnel mode gre ip
tunnel source loopback 0
 tunnel destination 192.0.2.1
 tunnel key 999
ip address 100.100.100.3 255.255.258
 ip nhrp network-id 1
ip nhrp authentication NHRPauth
ip nhrp nhs 100.100.100.1
ip nhrp map multicast 192.0.2.1
 ip nhrp map 100.100.100.1 192.0.2.1
ip mtu 1400
ip tcp adjust-mss 1360
router eigrp DMVPN TUNNEL NET
 address-family ipv4 unicast autonomous-system 68
eigrp router-id 3.3.3.3
 network 100.100.100.0 255.255.258.248
network 172.16.3.0 255.255.255.0
eigrp stub connected
router eigrp DMVPN TRANS NET
 address-family ipv4 unicast autonomous-system 168
```

```
eigrp router-id 30.3.3.3
   network 203.0.113.0 255.255.255.252
   network 192.168.3.0 255.255.255.0
   eigrp stub connected
   end
Layer 3 Switch DMVPN
   hostname DMVPN
  no ip domain lookup
  ip routing
  banner motd # DMVPN, DMVPN cloud switch #
  line con 0
   exec-timeout 0 0
   logging synchronous
   exit
  line vty 0 4
   privilege level 15
   password cisco123
   exec-timeout 0 0
   logging synchronous
   login
   interface g1/0/11
   no switchport
   ip address 192.0.2.2 255.255.255.252
   no shutdown
   exit
   interface g1/0/12
   no switchport
   ip address 198.51.100.1 255.255.255.252
   no shutdown
   exit
  interface g1/0/13
   no switchport
   ip address 203.0.113.1 255.255.255.252
   no shutdown
   exit
   router eigrp DMVPN TRANS NET
    address-family ipv4 unicast autonomous-system 168
   eigrp router-id 40.4.4.4
   network 192.0.2.0 255.255.255.252
   network 198.51.100.0 255.255.255.252
   network 203.0.113.0 255.255.255.252
   end
```

Instructions

Part 1: Build the Network and Configure Basic Device Settings

In Part 1, you will set up the network topology and configure basic settings if the network is not already configured. This lab uses the same topology and final configurations from the **Lab** - **Implement a DMVPN Phase 1 Hub-to-Spoke Topology**.

Step 1: Cable the network as shown in the topology.

Attach the devices as shown in the topology diagram, and cable as necessary.

Step 2: Configure initial settings for each router and the Layer 3 switch.

Console into each device, enter global configuration mode, and apply the initial settings for the lab if the devices are not already configured.

Step 3: Verify connectivity in the network.

a. From R1, ping the loopback interfaces of R2 and R3. All pings should be successful. This verifies that full connectivity exists in the underlay, or transport, network.

```
R1# ping 192.168.2.1
```

```
Type escape sequence to abort.
Sending 5, 100-byte ICMP Echos to 192.168.3.1, timeout is 2 seconds:
!!!!!
Success rate is 100 percent (5/5), round-trip min/avg/max = 1/1/1 ms
```

R1# ping 192.168.3.1

```
Type escape sequence to abort.
Sending 5, 100-byte ICMP Echos to 192.168.3.1, timeout is 2 seconds:
!!!!!
Success rate is 100 percent (5/5), round-trip min/avg/max = 1/1/1 ms
```

b. From R2 traceroute to the Loopback 1 interface of R3. You should see the following output. Note that traffic from the R2 spoke router travels through the R1 hub router to reach R3. This is the DMVPN Phase 1 traffic flow. Repeat the traceroute to verify this result.

R2# traceroute 172.16.3.1
Type escape sequence to abort.
Tracing the route to 172.16.3.1
VRF info: (vrf in name/id, vrf out name/id)
 1 100.100.100.1 1 msec 1 msec 1 msec
 2 100.100.100.3 1 msec * 2 msec

c. On the spoke routers, issue the **show ip route** command. Note that EIGRP shows the next hop for the Loopback 1 networks to be the R1 tunnel interface address. That is, both spoke routers will use R1 to send traffic on the overlay network to the LANs.

```
D
      192.168.3.0/24
           [90/16000] via 198.51.100.1, 00:21:21, GigabitEthernet0/0/1
      203.0.113.0/30 is subnetted, 1 subnets
         203.0.113.0
D
           [90/15360] via 198.51.100.1, 00:21:21, GigabitEthernet0/0/1
R3# show ip route eigrp | begin Gateway
Gateway of last resort is not set
      172.16.0.0/16 is variably subnetted, 3 subnets, 2 masks
         172.16.2.0/24 [90/102400640] via 100.100.100.1, 00:22:49, Tunnel1
D
      192.0.2.0/30 is subnetted, 1 subnets
         192.0.2.0 [90/15360] via 203.0.113.1, 00:22:59, GigabitEthernet0/0/1
D
D
      192.168.2.0/24
           [90/16000] via 203.0.113.1, 00:22:59, GigabitEthernet0/0/1
      198.51.100.0/30 is subnetted, 1 subnets
D
         198.51.100.0
           [90/15360] via 203.0.113.1, 00:22:59, GigabitEthernet0/0/1
```

Part 2: Configure DMVPN Phase 3

In this part of the lab, you will configure DMVPN Phase 3 to create DMVPN tunnels between the spoke routers. Initially, the services of the hub are required to begin data transfer over the VPN. However, the hub multipoint tunnel interface detects that traffic is "hairpinning," or exiting the interface on which it was received. The hub router sends redirect messages to the two spoke routers that are communicating. The spoke routers use the redirect messages to dynamically create a tunnel to connect to each other. In this way, the hub router does not need to forward spoke-to-spoke traffic after the setup of the spoke-to-spoke tunnel.

Step 1: Modify the tunnel interfaces on the spoke routers.

This lab builds on the Phase 1 lab that was previously completed. On the spoke routers R2 and R3, modify the configurations of the Tunnel 1 interfaces. The network will essentially be configured for DMVPN Phase 2 at the conclusion of this step.

a. On R2, set the tunnel mode to mGRE. You will see an error message that states that point-to-multipoint tunnels can not have static tunnel destinations configured.

R2(config) # interface tunnel 1

R2(config-if) # tunnel mode gre multipoint

Tunnel set mode failed. p2mp tunnels cannot have a tunnel destination.

b. Remove the tunnel destination configuration. You will see the interface go down and the EIGRP adjacency with the hub router be lost. Reconfigure the tunnel mode as GRE multipoint. You will see the interface come back up and the EIGRP adjacency will be restored.

R2(config-if) # no tunnel destination

*Mar 27 12:46:31.496: %LINEPROTO-5-UPDOWN: Line protocol on Interface Tunnell, changed state to down *Mar 27 12:46:31.499: %DUAL-5-NBRCHANGE: EIGRP-IPv4 68: Neighbor 100.100.100.1 (Tunnell) is down: interface down R2(config-if)# tunnel mode gre multipoint *Mar 27 12:46:46.629: %LINEPROTO-5-UPDOWN: Line protocol on Interface Tunnell, changed state to up

*Mar 27 12:46:48.008: %DUAL-5-NBRCHANGE: EIGRP-IPv4 68: Neighbor 100.100.100.1 (Tunnell) is up: new adjacency

- c. Repeat this process for the R3 tunnel interface. At this point, you have essentially configured DMVPN Phase 2. You may want to verify the R1 can ping R2 and R3 loopbacks again.
- d. Verify the tunnel interface configuration is now using mGRE with the **show interface tunnel 1** command.

R3# show interface tunnel 1 | include Tunnel protocol Tunnel protocol/transport multi-GRE/IP

Step 2: Modify the configuration on the spoke routers to enable NHRP routing shortcuts.

Configure the spoke router interfaces on R2 and R3 to enable NHRP to add spoke networks as next hops in the EIGRP routing table. The hub router will send NHRP redirect messages to the spokes. NHRP uses information in the redirect messages to manipulate the EIGRP routing table and create the next hop shortcuts.

R2(config)# interface tunnel 1
R2(config-if)# ip nhrp shortcut
R3(config)# interface tunnel 1
R3(config-if)# ip nhrp shortcut

Step 3: Modify the configuration of hub router to send NHRP redirect messages.

The Tunnel 1 interface of the hub router needs to be configured to send NHRP redirect messages to the spokes when it detects spoke-to-spoke traffic. Issue the **ip nhrp redirect** command on R1.

R1(config)# interface tunnel 1
R1(config-if)# ip nhrp redirect

Part 3: Verify DMVPN Phase 3

Now that DMVPN Phase 3 is complete, you can test dynamic spoke-to-spoke tunnel creation.

Step 1: Observe dynamic tunnel creation.

a. Return to R2. Initiate a traceroute to the simulated LAN interface on R3. The path will pass through R1 as it does in DMVPN Phase 1.

```
R2# traceroute 172.16.3.1
Type escape sequence to abort.
Tracing the route to 172.16.3.1
VRF info: (vrf in name/id, vrf out name/id)
    1 100.100.100.1 1 msec 1 msec 1 msec
    2 100.100.100.3 1 msec * 2 msec
```

b. Issue the traceroute command again. You will now see that R1 has enabled direct spoke-to-spoke communication between R2 and R3. This tunnel will expire after ten minutes by default. The tunnel dynamically reopens after data is sent to the spoke router again.

```
R2# traceroute 172.16.3.1
Type escape sequence to abort.
Tracing the route to 172.16.3.1
VRF info: (vrf in name/id, vrf out name/id)
   1 100.100.100.3 1 msec * 1 msec
```

c. Repeat the traceroute commands on R3 to 172.16.2.1.

Step 2: View the routing table.

a. On R2, issue the command to view the EIGRP routes that are in the routing table. Compare this routing table with the DMVPN Phase 1 routing from earlier in this lab. You should see that EIGRP shows the next hop interface to the 172.16.3.0 network to be the unchanged. However, the route is flagged with % indicating that NHRP is has overridden the next hop entry with its own value. Also notice that an NHRP route now appears in the routing table. This route indicates that the tunnel interface for R3 is considered to be directly connected by NHRP.

```
R2# show ip route
```

```
Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP
D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
E1 - OSPF external type 1, E2 - OSPF external type 2
i - IS-IS, su - IS-IS summary, L1 - IS-IS level-1, L2 - IS-IS level-2
ia - IS-IS inter area, * - candidate default, U - per-user static route
o - ODR, P - periodic downloaded static route, H - NHRP, 1 - LISP
a - application route
+ - replicated route, % - next hop override, p - overrides from PfR
```

Gateway of last resort is not set

	100.0.0.0/8 is variably subnetted, 3 subnets, 2 masks					
С	100.100.100.0/29 is directly connected, Tunnel1					
L	100.100.2/32 is directly connected, Tunnel1					
H	100.100.100.3/32 is directly connected, 00:03:53, Tunnel1					
	172.16.0.0/16 is variably subnetted, 3 subnets, 2 masks					
С	172.16.2.0/24 is directly connected, Loopback1					
L	172.16.2.1/32 is directly connected, Loopback1					
D	<pre>% 172.16.3.0/24 [90/102400640] via 100.100.100.1, 02:53:00, Tunnel1</pre>					
	192.0.2.0/30 is subnetted, 1 subnets					
D	192.0.2.0 [90/15360] via 198.51.100.1, 03:38:15, GigabitEthernet0/0/1					
	192.168.2.0/24 is variably subnetted, 2 subnets, 2 masks					
С	192.168.2.0/24 is directly connected, Loopback0					
L	192.168.2.1/32 is directly connected, Loopback0					
D	192.168.3.0/24					
	[90/16000] via 198.51.100.1, 03:38:15, GigabitEthernet0/0/1					
	198.51.100.0/24 is variably subnetted, 2 subnets, 2 masks					
С	198.51.100.0/30 is directly connected, GigabitEthernet0/0/1					
L	198.51.100.2/32 is directly connected, GigabitEthernet0/0/1					
	203.0.113.0/30 is subnetted, 1 subnets					
D	203.0.113.0					
	[90/15360] via 198.51.100.1, 03:38:15, GigabitEthernet0/0/1					

b. View the value that is actually used for the next hop address. It is marked with NHO for next hop override. This indicates that the next hop to 172.16.3.0 is R3 through the spoke-to-spoke tunnel.

R2# show ip route next-hop-override | begin Gateway Gateway of last resort is not set

100.0.0.0/8 is variably subnetted, 3 subnets, 2 masks 100.100.100.0/29 is directly connected, Tunnel1

С

```
L
        100.100.2/32 is directly connected, Tunnel1
Η
        100.100.3/32 is directly connected, 00:17:39, Tunnel1
      172.16.0.0/16 is variably subnetted, 3 subnets, 2 masks
С
        172.16.2.0/24 is directly connected, Loopback1
L
        172.16.2.1/32 is directly connected, Loopback1
D
        172.16.3.0/24 [90/102400640] via 100.100.100.1, 00:17:41, Tunnel1
   2
                       [NHO][90/255] via 100.100.100.3, 00:17:39, Tunnel1
      192.0.2.0/30 is subnetted, 1 subnets
D
        192.0.2.0 [90/15360] via 198.51.100.1, 01:02:56, GigabitEthernet0/0/1
      192.168.2.0/24 is variably subnetted, 2 subnets, 2 masks
С
        192.168.2.0/24 is directly connected, Loopback0
        192.168.2.1/32 is directly connected, Loopback0
L
D
     192.168.3.0/24
           [90/16000] via 198.51.100.1, 01:02:56, GigabitEthernet0/0/1
     198.51.100.0/24 is variably subnetted, 2 subnets, 2 masks
        198.51.100.0/30 is directly connected, GigabitEthernet0/0/1
С
        198.51.100.2/32 is directly connected, GigabitEthernet0/0/1
L
      203.0.113.0/30 is subnetted, 1 subnets
        203.0.113.0
D
           [90/15360] via 198.51.100.1, 01:02:56, GigabitEthernet0/0/1
```

Step 3: Verify the DMVPN

a. View the DMVPN information with the spoke-to-spoke tunnel open. The first entry in the table is the static tunnel between R2 and the hub router. The DLX flag indicates that the entry is the local network. The DT1 entry is the route through the overlay network, and the DT2 entry the next hop override to the target network. If the spoke-to-spoke tunnel has closed, generate traffic to reopen it with traceroute.

```
R2# show dmvpn detail
Legend: Attrb --> S - Static, D - Dynamic, I - Incomplete
      N - NATed, L - Local, X - No Socket
      T1 - Route Installed, T2 - Nexthop-override
      C - CTS Capable, I2 - Temporary
      # Ent --> Number of NHRP entries with same NBMA peer
      NHS Status: E --> Expecting Replies, R --> Responding, W --> Waiting
      UpDn Time --> Up or Down Time for a Tunnel
_____
Interface Tunnel1 is up/up, Addr. is 100.100.100.2, VRF ""
  Tunnel Src./Dest. addr: 192.168.2.1/Multipoint, Tunnel VRF ""
  Protocol/Transport: "multi-GRE/IP", Protect ""
  Interface State Control: Disabled
  nhrp event-publisher : Disabled
IPv4 NHS:
100.100.100.1 RE priority = 0 cluster = 0
Type:Spoke, Total NBMA Peers (v4/v6): 3
# Ent Peer NBMA Addr Peer Tunnel Add State UpDn Tm Attrb Target Network
_____ _____
   1 192.0.2.1
                   100.100.100.1 UP 03:22:47 S 100.100.1/32
   1 192.168.2.1
                   100.100.100.2 UP 00:01:36 DLX 100.100.100.2/32
```

2 192.168.3.1	100.100.100.3	UP 00:01:36	DT1	100.100.100.3/32
192.168.3.1	100.100.100.3	UP 00:01:36	DT2	172.16.3.0/24

```
Crypto Session Details:
```

Pending DMVPN Sessions:

b. Repeat this command on R3.

Step 4: View NHRP Mappings

Note: If it has been more than 10 minutes since you completed your traceroutes, repeat them now to reestablish the spoke-to-spoke tunnels.

a. On R2 and R3, issue the **show ip nhrp detail** command to view the NHRP information for the routers. Note the correspondence between the entries in the output of this command with the output from the **show dmvpn detail** command. The first entry is the static entry to the hub router. The second entry is the local route, corresponding to the DTX entry in output above. The third entry corresponds to the DT1 entry and is flagged with **router nhop rib**. This indicates that the router has an explicit method to reach the tunnel IP address using an NBMA address and has an associated route installed in the routing table.

The flag **rib nho** indicates that the router has found an identical route in the routing table that belongs to a different protocol (EIGRP in this case.). NHRP has overridden the other protocol's next-hop entry for the network by installing a next-hop shortcut in the routing table. This corresponds to the DT2 entry in the **show dmvpn detail** output.

```
R2# show ip nhrp detail
100.100.100.1/32 via 100.100.100.1
   Tunnell created 04:03:01, never expire
   Type: static, Flags:
  NBMA address: 192.0.2.1
   Preference: 255
100.100.100.2/32 via 100.100.100.2
   Tunnel1 created 00:00:21, expire 00:09:38
   Type: dynamic, Flags: router unique local
  NBMA address: 192.168.2.1
   Preference: 255
    (no-socket)
  Requester: 100.100.100.3 Request ID: 9
100.100.100.3/32 via 100.100.100.3
   Tunnel1 created 00:00:21, expire 00:09:38
   Type: dynamic, Flags: router nhop rib
  NBMA address: 192.168.3.1
   Preference: 255
172.16.3.0/24 via 100.100.100.3
   Tunnel1 created 00:00:21, expire 00:09:38
   Type: dynamic, Flags: router rib nho
   NBMA address: 192.168.3.1
   Preference: 255
```

b. You have successfully configured a DMVPN Phase 3 network.

Router Model	Ethernet Interface #1	Ethernet Interface #2	Serial Interface #1	Serial Interface #2
1800	Fast Ethernet 0/0 (F0/0)	Fast Ethernet 0/1 (F0/1)	Serial 0/0/0 (S0/0/0)	Serial 0/0/1 (S0/0/1)
1900	Gigabit Ethernet 0/0 (G0/0)	Gigabit Ethernet 0/1 (G0/1)	Serial 0/0/0 (S0/0/0)	Serial 0/0/1 (S0/0/1)
2801	Fast Ethernet 0/0 (F0/0)	Fast Ethernet 0/1 (F0/1)	Serial 0/1/0 (S0/1/0)	Serial 0/1/1 (S0/1/1)
2811	Fast Ethernet 0/0 (F0/0)	Fast Ethernet 0/1 (F0/1)	Serial 0/0/0 (S0/0/0)	Serial 0/0/1 (S0/0/1)
2900	Gigabit Ethernet 0/0 (G0/0)	Gigabit Ethernet 0/1 (G0/1)	Serial 0/0/0 (S0/0/0)	Serial 0/0/1 (S0/0/1)
4221	Gigabit Ethernet 0/0/0 (G0/0/0)	Gigabit Ethernet 0/0/1 (G0/0/1)	Serial 0/1/0 (S0/1/0)	Serial 0/1/1 (S0/1/1)
4300	Gigabit Ethernet 0/0/0 (G0/0/0)	Gigabit Ethernet 0/0/1 (G0/0/1)	Serial 0/1/0 (S0/1/0)	Serial 0/1/1 (S0/1/1)

Router Interface Summary Table

Note: To find out how the router is configured, look at the interfaces to identify the type of router and how many interfaces the router has. There is no way to effectively list all the combinations of configurations for each router class. This table includes identifiers for the possible combinations of Ethernet and Serial interfaces in the device. The table does not include any other type of interface, even though a specific router may contain one. An example of this might be an ISDN BRI interface. The string in parenthesis is the legal abbreviation that can be used in Cisco IOS commands to represent the interface.

Device Configs – Final

Router R1

enable configure terminal hostname R1 no ip domain lookup banner motd # R1, Implement DMVPN Hub # line con 0 exec-timeout 0 0 logging synchronous exit line vty 0 4 privilege level 15 password cisco123 exec-timeout 0 0 logging synchronous login exit interface g0/0/1 ip address 192.0.2.1 255.255.255.252 no shutdown

```
exit
interface tunnel 1
tunnel mode gre multipoint
tunnel source g0/0/1
tunnel key 999
ip address 100.100.100.1 255.255.258.248
ip nhrp network-id 1
ip nhrp authentication NHRPauth
ip nhrp map multicast dynamic
ip nhrp redirect
bandwidth 4000
ip mtu 1400
ip tcp adjust-mss 1360
exit
router eigrp DMVPN TUNNEL NET
address-family ipv4 unicast autonomous-system 68
eigrp router-id 1.1.1.1
network 100.100.100.0 255.255.258.248
af-interface tunnel 1
no split-horizon
router eigrp DMVPN TRANS NET
address-family ipv4 unicast autonomous-system 168
eigrp router-id 10.1.1.1
network 192.0.2.0 255.255.255.252
end
```

Router R2

```
enable
configure terminal
hostname R2
no ip domain lookup
banner motd # R2, Implement DMVPN Spoke 1 #
line con 0
exec-timeout 0 0
logging synchronous
exit
line vty 0 4
privilege level 15
password cisco123
exec-timeout 0 0
logging synchronous
login
exit
interface g0/0/1
ip address 198.51.100.2 255.255.255.252
no shutdown
exit
interface loopback 0
ip address 192.168.2.1 255.255.255.0
```

```
no shutdown
exit
interface loopback 1
ip address 172.16.2.1 255.255.255.0
no shutdown
exit
interface tunnel 1
tunnel mode gre multipoint
tunnel source loopback 0
no tunnel destination
tunnel key 999
ip address 100.100.100.2 255.255.258.248
ip nhrp network-id 1
ip nhrp authentication NHRPauth
ip nhrp nhs 100.100.100.1
ip nhrp map multicast 192.0.2.1
ip nhrp map 100.100.100.1 192.0.2.1
ip nhrp shortcut
ip mtu 1400
ip tcp adjust-mss 1360
router eigrp DMVPN TUNNEL NET
address-family ipv4 unicast autonomous-system 68
eigrp router-id 2.2.2.2
network 100.100.100.0 255.255.258.248
network 172.16.2.0 255.255.255.0
eigrp stub connected
router eigrp DMVPN TRANS NET
address-family ipv4 unicast autonomous-system 168
eigrp router-id 20.2.2.2
network 198.51.100.0 255.255.255.252
network 192.168.2.0 255.255.255.0
end
```

Router R3

enable configure terminal hostname R3 no ip domain lookup banner motd # R3, Implement DMVPN Spoke 2 # line con 0 exec-timeout 0 0 logging synchronous exit line vty 0 4 privilege level 15 password ciscol23 exec-timeout 0 0 logging synchronous loggin

exit interface g0/0/1 ip address 203.0.113.2 255.255.255.252 no shutdown exit interface loopback 0 ip address 192.168.3.1 255.255.255.0 no shutdown exit interface loopback 1 ip address 172.16.3.1 255.255.255.0 no shutdown exit interface tunnel 1 tunnel mode gre multipoint tunnel source loopback 0 no tunnel destination tunnel key 999 ip address 100.100.100.3 255.255.258.248 ip nhrp network-id 1 ip nhrp authentication NHRPauth ip nhrp nhs 100.100.100.1 ip nhrp map multicast 192.0.2.1 ip nhrp map 100.100.100.1 192.0.2.1 ip nhrp shortcut ip mtu 1400 ip tcp adjust-mss 1360 router eigrp DMVPN TUNNEL NET address-family ipv4 unicast autonomous-system 68 eigrp router-id 3.3.3.3 network 100.100.100.0 255.255.258.248 network 172.16.3.0 255.255.255.0 eigrp stub connected router eigrp DMVPN TRANS NET address-family ipv4 unicast autonomous-system 168 eigrp router-id 30.3.3.3 network 203.0.113.0 255.255.255.252 network 192.168.3.0 255.255.255.0 eigrp stub connected end